

Using WUMgr to Update a Windows 10 System

- 1) Make and verify a full system backup.
- 2) Open WUMgr, and click on the **“Auto Update”** tab.
- 3) Un-check (un-select) these two program options:
 - a) **Block Access to WU Servers**
 - b) **Disable Store Auto Update**
- 4) Click the radio button labeled **“Automatic Update (default)”**
 - a) Click **“OK”** on the message box *“For the new configuration to fully take effect ...”*
- 5) Close WUMgr. Then restart the system.
- 6) Once restarted, log back in. Then re-open WUMgr.
- 7) Click the **“Windows Update”** button. Then click the **“Search”** button.



- 8) Wait while WUMgr does a Check for Updates (a few seconds to several minutes).
- 9) When the check finishes you should see a list of all available updates.
- 10) Check (select) any updates that you want to hide. Then click the **“Hide”** button.



- 11) Check (select) any updates that you want to install. Then click the **“Install”** button.



- 12) Wait while WUMgr downloads and installs the selected updates (possibly several minutes).
- 13) Once the updating finishes you will probably be prompted to restart the system.
 - a) Click **“OK”** on the message box (if present) that a *“reboot is required”*.
- 14) Close WUMgr. Then restart the system.
- 15) Once restarted, log back in. Then re-open WUMgr.
- 16) Re-check for more updates by repeating steps 7 thru 13 until no more updates are found.
- 17) Click on the **“Auto Update”** tab. Then check (select) these program options:
 - a) **Block Access to WU Servers**
 - b) **Hide WUSettings Page** (this should already be selected/checked)
 - c) **Disable Store Auto Update**
- 18) Click the radio button labeled **“Disable Automatic Update”**.
- 19) Check (select) the box labeled **“Disable Update Facilitators”**.
 - a) Click **“OK”** on the message box *“For the new configuration to fully take effect ...”*
- 20) Close WUMgr. Then restart the system. You’re done.